

## Developer Guide

---

# Enable ADB on Handheld Device

This page is intentionally left blank.

**Copyrights and proprietary notice****Hardware documentation:**

Copyrights © 2004-2022 of DERMALOG Identification Systems GmbH. All rights reserved. This hardware documentation is property of DERMALOG Identification Systems GmbH. The documentation or parts thereof may in no way be copied, distributed or translated, neither in electronic, manual, optical nor any other manner, unless prior approval by DERMALOG Identification Systems GmbH. This documentation serves information purposes only. The data contained in the examples are fictitious, unless otherwise noted. DERMALOG Identification Systems GmbH is not liable for any direct or indirect damages because of or in connection with the use of the documentation as far as there is no deliberate or grossly negligent conduct.

**Right to copy**

DERMALOG Identification Systems GmbH permits the hardware buyer the production of copies for internal purposes only. Each copy has to contain all notices on any copyrights, trademark rights, service marks or other intellectual property rights. The hardware buyer has to consecutively number the copies. In addition, DERMALOG Identification Systems GmbH reserves right to revise or change the documentation at any time without having to inform the parties about it.

**Software documentation:**

Copyrights © 2004-2022 of DERMALOG Identification Systems GmbH. All rights reserved. This software documentation is property of DERMALOG Identification Systems GmbH and is made available in connection with a license agreement. This documentation may be used or copied only in accordance with the conditions of the license agreement. The documentation or parts thereof may in no way be copied, distributed or translated, neither in electronic, manual, optical nor any other manner, unless prior approval by DERMALOG Identification Systems GmbH is given or this is expressly provided for in the license agreement. This documentation serves information purposes only. The data contained in the examples are fictitious, unless otherwise noted. DERMALOG Identification Systems GmbH is not liable for any direct or indirect damages because of or in connection with the use of the documentation as far as there is no deliberate or grossly negligent conduct.

**Right to copy**

The license agreement of DERMALOG Identification Systems GmbH permits the licensee the production of copies for internal purposes only. Each copy has to contain all notices on any copyrights, trademark rights, service marks or other intellectual property rights. The licensee has to consecutively number the copies. In addition, DERMALOG Identification Systems GmbH reserves right to revise or change the documentation at any time without having to inform the parties about it.

## Revision history

Document Version	Date	Author	Changes
1.0	2022-01-21	DERMALOG	Initial document

Table 1: Revision history

## Table of contents

Introduction.....	5
Safety instructions.....	5
1     Enable USB debugging.....	6
2     Change USB mode.....	7
3     Enable ADB via WiFi .....	8

## Introduction

This developer guide describes how to enable the Android Debug Bridge (ADB) on a DERMALOG handheld device. The handheld device runs an Android operating system.

## Safety instructions

### **NOTICE**

Do not disassemble, modify, repair, remove parts, or open the housing of the DERMALOG handheld device, unless expressly authorized by DERMALOG. Disregarding this warning can result in serious damage to the handheld device and will cause the loss of any warranty. If the warranty label is damaged, all warranty claims are void.


---

# 1 Enable USB debugging


## Prerequisites:


- The **Home** screen is shown.


## START:




1. On the **Home** screen, swipe a finger upwards.  
► The **Apps** screen is shown.




2. Open the **Settings** menu .
3. Go down to the entry **System**.




4. Open the **System** menu.




5. Open the **About device** menu.
6. Go down to the entry **Build number**.




7. Tap **Build number** 7 times.
  - ▶ The message *You are now a developer!* is shown.

8. At the top of the screen, tap .
  - ▶ The **System** menu is shown.



9. Open the **Developer options** menu.
10. Enable **USB debugging**.




**FINISH: You have enabled USB debugging.**

## 2 Change USB mode


If you want to connect the handheld to an external device via USB cable and the connection is not working, you have to change the USB mode.

**START:**

1. Select **Settings > System > About device**.



2. Tap **Custom build number** 6 times.



3. Select one of the following options:

**OPEN:**

- External device can be connected via USB cable for ADB or file transfer.
- No internal USB device can be used (e.g. fingerprint scanner).

**CLOSE:**

- No external device can be connected via USB cable.
- Internal USB devices can be used (e.g. fingerprint scanner).

**FINISH: You have changed the USB mode.**

### 3 Enable ADB via WiFi


---

**Prerequisites:**

- The handheld device is switched on and connected to a WiFi network.
  - The USB mode is *Open*. (See section 2.)
  - The handheld's IP address is known (**Settings > System > About device > IP address**).
  - ADB (Android Debug Bridge) has been installed on the computer and is running.
- 

**START:**

1. Connect a USB cable between the handheld and the computer.
2. On the computer, open the command prompt and execute the following commands:
  - a. `adb devices`
    - The devices attached via USB are listed.
  - b. `adb tcpip 5555`
    - The ADB is now running over TCP/IP mode with port : 5555
3. Disconnect the USB cable.
4. Execute the following commands:
  - a. `adb connect <IP address handheld >`
  - b. `adb devices`
    - The devices attached via WiFi are listed.



```
Microsoft Windows [Version 10.0.19044.1466]
(c) Microsoft Corporation. All rights reserved.

U:\>adb devices
List of devices attached
MP0621096D7C98F device

U:\>adb tcpip 5555
restarting in TCP mode port: 5555

U:\>adb connect 192.168.178.58
connected to 192.168.178.58:5555

U:\>adb devices
List of devices attached
192.168.178.58:5555 device

U:\>
```

5. Set the USB mode to *Close*. See section 2.

**FINISH:** You have enabled ADB via WiFi.



This page is intentionally left blank.

More information:



#### Internet

Receive further Information on our company website  
[www.dermalog.com](http://www.dermalog.com)

#### Head Office

DERMALOG Identification Systems GmbH  
Mittelweg 120  
20148 Hamburg  
Germany  
Tel: +49 (0) 40 41 32 27 0  
Fax: +49 (0) 40 41 32 27 89  
[info@dermalog.com](mailto:info@dermalog.com)

#### Berlin Office

DERMALOG Identification Systems GmbH  
Kronenstrasse 1  
10117 Berlin  
Germany

#### Dubai Office

DERMALOG FZE  
Business Center, Al Shmookh Building  
UAQ Free Trade Zone  
Umm Al Quwain, U.A.E.

#### Malaysia Office

DERMALOG Afis Asia Sdn Bhd  
8-4, 8th Floor, Bangunan Malaysian RE,  
No.17, Lorong Dungun, Damansara Height,  
50490 Kuala Lumpur, Malaysia  
Tel: +60-3-20921316  
Fax: +60-3-20921690  
[asia@dermalog.com](mailto:asia@dermalog.com)

#### Philippine Branch Office

DERMALOG Identification Systems GmbH  
7/F Unit B 8 Rockwell  
Hidalgo Drive, Rockwell Center  
Makati City 1210  
Philippines  
Tel: +63 2 683 7500  
Fax: +63 2 856 1138  
[office.manila@dermalog.com](mailto:office.manila@dermalog.com)

#### Singapore Office

DERMALOG Singapore  
Technical Services Pte. Ltd.  
Southbank  
883 North Bridge Road, #17-02  
198785 Singapore  
[asia@dermalog.com](mailto:asia@dermalog.com)



© 2022 All content and images are owned by DERMALOG Identification Systems GmbH and are protected by copyright.